

关于 T3 PC 软件及升级固件说明

About T3 PC software and firmware upgrade instructions

1. 首先打开网站地址 <http://en.atorch.cn/NewsDetail.aspx?ID=100>

First, open the website address <http://en.atorch.cn/NewsDetail.aspx?ID=100>


T3 User Manual


🕒 2026-05-25 👁 59




2. 把 T3 PC 软件下载到您的电脑中，无需安装，直接解压使用

Download T3 PC software to your computer without installation, simply unzip and use it



3. 双击打开  T3 USB tester PC 软件,然后将 USB 数据线插入 T3 测试仪的 HID 联机口!

Double click  to open T3 USB tester PC software, Then plug the USB data cable into the HID port of the T3 tester!



4. 然后将 T3 测试仪插入 C 口充电器，输出接好测试数码设备，即可完成连接

Then insert the T3 tester into the C-port charger, connect the output to the testing digital device, and the connection is complete




5. PC 软件会实时显示充电，电压，功率，并显示曲线！观察其数据变化，并可导出数据！

The PC software will display charging, voltage, power, and curves in real time! Observe its data changes and export the data!




6. 软件左上面可点击切换中文/英文显示

Click on the top left corner of the software to switch between Chinese/English display





7. 点击软件左边设置图标，可进去软件设置,设备重启之后，会生效

Click on the settings icon on the left side of the software to enter the software settings, After the device restarts, it will take effect




8. 软件后台设置功能 Software background setting function




9. 点击软件右上角  固件升级，可进入固件升级页面

Click on the firmware upgrade button in the upper right corner of the software to enter the firmware upgrade page





10. 进入此界面之后，请打开红色框，选择您需要升级的固件

After entering this interface, please open the red box and select the firmware you need to upgrade



11. 选择 bin 升级固件文件，点击开始下载，即可进入升级程序滚动条


Select the bin upgrade firmware file, click on start download to enter the upgrade program scroll bar





12. 升级完之后，固件版本会显示最新版本(例如 2.0.4)

After the upgrade, the firmware version will display the latest version (e.g. 2.0.4)



13.APP Download address

1.IOS APP: search E_test on iphone APP store to download

<https://apps.apple.com/cn/app/e-test/id1478623332>

2. Android APP: search E-test at Google play to down load or

<http://en.atorch.cn/upload/file/20260526/6391540453650635427048055.zip>